

Preventing Surgical Infection



Preventing Surgical Infection

- An “outside to in” concept



American Academy of Orthopaedic Surgeons
AAOS American Association of Orthopaedic Surgeons

Preventing Surgical Infection

- **Environmental Control**
 - ◆ **Operating Room Environment**
 - ◆ **Patient Environment**
 - ◆ **Wound Environment**



Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**
 - ◆ **Keep doors closed and limit traffic in and out of the operating room**
 - ◆ **Eliminate needless activity**
 - ◆ **Eliminate needless personnel**



Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**
 - **Use standard scrub attire, sterile gloves, gowns and drapes to decrease wound contamination and exposure of health care workers (HCWs).**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**
 - ◆ **No visible hair or nose**
 - ◆ **Change mask and scrubs**
 - ◆ **Strict adherence to OR discipline and Universal Precautions**



Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**

- ◆ **Hand hygiene**

- ◆ **Provide personnel with efficacious hand-hygiene products that have low irritancy potential**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

■ Operating Room Environment

◆ Hand hygiene

- ◆ The cost of hand-hygiene products should not be the primary factor influencing product selection



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**

- ◆ **Hand hygiene**

- ◆ **Newer alcohol and CHG based hand lotions appear to provide more effective antiseptics than standard scrub**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

■ Operating Room Environment

◆ Hand hygiene

- ◆ To maximize acceptance of hand-hygiene products, solicit input from employees regarding the feel, fragrance, and skin tolerance of all products under consideration.



American Academy of Orthopaedic Surgeons



American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

■ Operating Room Environment

◆ Hand hygiene

- ◆ Provide health care workers with hand lotions or creams to minimize the occurrence of irritant contact dermatitis associated with hand antiseptics or hand washing



American Academy of Orthopaedic Surgeons



American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

■ Operating Room Environment

◆ Hand hygiene

- ◆ Healthcare personnel are more likely to comply with hand hygiene procedures if senior medical staff people or peers are seen to be compliant



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**
 - **Sterilize all surgical instruments according to published guidelines**
 - **Ethylene oxide has been classified as a carcinogen and is being replaced by H₂O₂ sterilization procedures**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**
 - ◆ **maintain positive pressure in the conventional operating room and provide greater than 15 operating room volumes exchanges per hour**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**
 - ◆ **Laminar Flow - Consider performing orthopedic implant operations in operating rooms with ultra clean air and body exhaust suites - CDC**



Preventing Surgical Infection Environmental Control



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**
 - ◆ **Laminar Flow - After decades of clean-air operating rooms, no uniform opinion about the efficiency in preventing infections has been achieved**



Preventing Surgical Infection

Environmental Control

- **Operating Room Environment**
 - ◆ **Laminar Flow - with an infection rate of around 1% only a very large series of homologous surgical cases will show statistical significance**



Preventing Surgical Infection

Environmental Control

■ Patient Environment

- ◆ **Laminar Flow and body exhaust suits in combination with other infection control measures appears to improve infection rates**



AAOS

American Academy of Orthopaedic Surgeons
American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

■ Patient Environment

- ◆ Monitor and maintain normal glycemia
- ◆ Maintain normothermia (above 36 degrees).



Preventing Surgical Infection

Environmental Control

■ Patient Environment

◆ Antimicrobial Prophylaxis

- ◆ Give the initial dose within one hour preceding incision
- ◆ Use the appropriate antimicrobial and dosing



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

■ Patient Environment

◆ Antimicrobial Prophylaxis

- ◆ Repeat the dose during surgery as needed to maintain blood levels - CDC



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

■ Patient Environment

◆ Antimicrobial Prophylaxis

- ◆ Stop prophylactic antimicrobials within 24 hours
- ◆ Discontinue use even with catheters or drains still in place



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

■ Patient Environment

◆ Antimicrobial Prophylaxis

- ◆ Know your hospital antibiogram
- ◆ Know your formulary
- ◆ Know your patient population



Preventing Surgical Infection

Environmental Control

- Patient Environment
 - ◆ Antimicrobial Prophylaxis
 - ◆ vancomycin is appropriate for prophylaxis for major surgical procedures involving implantation of prosthetic materials or devices at institutions that have a high rate of infections caused by MRSA or MRSE



American Academy of Orthopaedic Surgeons

AAOS American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

- **Patient Environment**
 - ◆ **Antimicrobial Prophylaxis**
 - ◆ **vancomycin is appropriate for prophylaxis for a patient who has a life-threatening allergy to beta-lactam antibiotics**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

- **Patient Environment**
 - ◆ **Antimicrobial Prophylaxis**
 - **Vancomycin should be used to treat known infections, not for routine prophylaxis**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

- **Patient Environment**
 - ◆ **Antimicrobial Prophylaxis**
 - ◆ **vancomycin is not appropriate for infection or colonization of indwelling central or peripheral catheters**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection

Environmental Control

■ Wound Environment

- ◆ Perform proper skin preparation to decrease Surgical Site Infection (SSI)

- ◆ Hair Removal

- ◆ Skin Preparation

- ◆ Incise Drapes



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection Wound Environment

- **Perform proper skin preparation**
 - ◆ **Method of hair removal**
 - ◆ **Razor = 5.6% SSI rates**
 - ◆ **Depilatory = 0.6% SSI rates**
 - ◆ **No hair removal = 0.6% SSI rates**
 - ◆ **Electric shaver alternative**



Preventing Surgical Infection Wound Environment

- **Timing of hair removal**
 - ◆ **Shaving immediately before = 3.1% SSI rates**
 - ◆ **Shaving \leq 24 hrs before = 7.1% SSI rates**
 - ◆ **Shaving $>$ 24 hrs before = 20% SSI rates**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection Wound Environment

- **Timing of hair removal**
 - ◆ **Don't use safety razor**

Preventing Surgical Infection Wound Environment

■ Skin Preparation

- ◆ preoperative skin prep of the surgical field including alcohol, iodophors and chlorhexidene gluconate



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection Wound Environment

- **Incise Drapes**

- ◆ **Modifications to these procedures include skin preparation and incise drape application**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection Wound Environment

■ Incise Drapes

- ◆ **Skin Preparation and operation was associated with a six fold increase in infection rate when compared with operations in which the incise drape did not lift**



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection Wound Environment

■ Incise Drapes

- ◆ In another randomized, prospective study use of this system documented decreased cost with use



American Academy of Orthopaedic Surgeons

AAOS

American Association of Orthopaedic Surgeons

Preventing Surgical Infection



American Academy of Orthopaedic Surgeons
AAOS American Association of Orthopaedic Surgeons

Preventing Surgical Infection Wound Environment

- **Surgical technique**
 - ◆ **Minimize operative time**
 - ◆ **Maintain hemostasis, gentle handling of tissue, eradicate dead space, remove dead tissue and foreign bodies as needed, close over drain when indicated.**



American Academy of Orthopaedic Surgeons

AAOS American Association of Orthopaedic Surgeons

Preventing Surgical Infection Wound Environment

- **Surgical technique**
 - ◆ **Sterile dressing**
 - ◆ **Post operative surveillance for SSI**

